


# PROCESSING YOUR BLACK & WHITE FILM




Turn on the tap until the lines align. This will give you the correct temperature.




Fill the tempered water in the measuring cup.



Wear gloves, apron and safety goggles.



Measure off the developer.



Mix the solution with water.



Take the required amount of stop.  
Do not dilute stop bath from tub.



Take the required amount of fix.  
Do not dilute fixer from tub.



Place the cups on the basin.



Lay out the developing tank in a logical order so that you can find them in the dark.



Close the door and switch to the 2.


## IN TOTAL DARKNESS



Open a film cassette. Use the rounded end of the bottle cap opener to pry off the flat end of the cassette.



Cut off the tongue to make the end of the film square. Also cut off the corners. Hold the film loosely by its edges.



Push the film about 5cm into the reel. Wind the film into the reel by turning the two halves of the reel forwards and backwards.



Cut the spool free when all the film is wound. Put the reel in the tank and cover it.



When the loaded reel is in the tank with the cover securely in place you can turn on the lights.




Start the timer and pour the developer into the tank. Begin agitation immediately. Invert tank for the first 30 sec and then for 5 sec every half minute.



When developing time is up, pour out the developer.



Pour the stop bath into the tank. Agitate continuously by gently swirling and inverting the tank.



Pour out the stop bath back into the tub.



Pour the fixer into the tank. Agitate first 30 sec and then 10 sec every half minute.




Pour out the fixer back into the tub.




Fill the tank with water. Invert the tank 5 times. Drain it away and refill. Invert the tank 10 times. Once more, drain the water. Invert the tank 20 times and drain it away. Repeat the last step three times.



Fill the tank with water. Add a few drops of wetting agent to the water. The film remains in the solution for 30 sec, agitating gently for 5 sec.



Run film between index and middle finger from top to bottom or use a clean squeegee made for photo purposes.



Attach clothes pin to the beginning and end of film as a bottom weight. Hang the film on the dryer. Press both buttons on the dryer and set to 40 min.

Rinse your hands, the reel, tank, basin, and any other equipment that came in contact with chemicals thoroughly.